



Smart Editor Ver. 1.0.2.0 Update Information

	V10	V9	TSi/TS	V8i(N)/V8(N)	X1
System program	Ver. 1.400	Ver. 3.200	Ver. 2.450	Ver. 2.390	Ver. 1.900 ^{*2}
OS	Ver. 1.50 ^{*1}	Ver. 5.00 ^{*1}			

^{*1} Storage is necessary for updating.

^{*2} Please download the X1 update program from our website. For the update procedure, refer to the "Update procedure" provided with the update program.

Connection

- 1** Additional connectable device: Fuji Electric FRENIC-MEGA(G2) (MODBUS TCP/IP)
 Applicable model: V10/V9/TSi/X1
 Device: Fuji Electric FRENIC-MEGA(G2)(MODBUS TCP/IP)

- 2** Additional connectable device: Fuji Electric FRENIC-Ace(E3) (MODBUS TCP/IP)
 Applicable model: V10/V9/TSi/X1
 Device: Fuji Electric FRENIC-Ace(E3)(MODBUS TCP/IP)

- 3** Additional connectable device: Fuji Electric FRENIC-Ace(E3) (MODBUS RTU)
 Applicable model: V10/V9/TSi/TS/X1
 Device: Fuji Electric FRENIC-Ace(E3)(MODBUS RTU)

- 4** Additional connectable device: MITSUBISHI ELECTRIC iQ-R Series TAG (Built-in Ethernet)
 Applicable model: V10/V9/TSi/X1
 Device: MITSUBISHI ELECTRIC iQ-R Series TAG (Build-in Ethernet)
 <Overview>
 Both tag and PLC device can be used.

- 5** Additional connectable device: KEYENCE KV-8000 Tag (Ethernet UDP/IP)
 Applicable model: V10/V9/TSi/X1
 Device: KEYENCE KV-8000 Tag (Ethernet UDP/IP)
 <Overview>
 Both tag and PLC device can be used.

- 6** Additional connectable device: CHINO LT23A (MODBUS RTU)
 Applicable model: V10/V9/TSi/TS/V8i(N)/V8(N)/X1
 Device: CHINO LT23A (MODBUS RTU)

- 7** Ladder program transfer extended specifications: 1:n connection supported
 Applicable model: V10/V9/TSi/TS
 Device: Fuji Electric FRENIC series (loader)
 Fuji Electric FRENIC-MEGA(G2) (MODBUS RTU)
 Fuji Electric FRENIC-Ace(E3) (MODBUS RTU)
 <Overview>
 The ladder transfer function supports 1:n connection for some models.

- 8** Ethernet(TCP/IP)connection extended specifications: Dynamic allocation of communication port numbers
 Applicable model: V10/V9/X1
 <Overview>
 The communication port numbers of MONITOUCH can be dynamically allocated when connecting to a PLC via TCP/IP.
 <Setting location>
 Project View -> [Hardware Settings] tab -> [MONITOUCH Settings] -> [Unit Settings] -> [General Settings] -> [PLC]
 -> [Dynamically allocate PLC communication port for TCP/IP] checkbox

- 9** Ethernet connection extended specifications: KeepAlive supported
 Applicable model: X1/TELLUS5/TELLUS4/TELLUS4 (iPad)
 <Overview>
 KeepAlive function is now supported when connecting to a PLC via Ethernet.
 If communication is not available, it can be detected more quickly.
 <Setting location>
 Project View -> [Hardware Settings] tab -> [Connection Device] -> [8Way Communication] -> [PLCn Properties] ->
 [Comm. Error Handling: Disconnect] -> select [Use KeepAlive: Yes] and [KeepAlive] checkbox in PLC Table

Function

1 Video input/RGB input/RGB output supported

*** OS updating is necessary**

Applicable model: V10xxiSxxG

Optional unit model : GUX-00: Video input 4ch GUX-04: Video input 1ch
 GUX-01: RGB input 1ch GUX-11: RGB input 2ch
 GUX-02: RGB output 1ch
 GUX-10: Video input 2ch + RGB input 1ch

<Overview>

By attaching an optional unit "GUX-xx" onto G-type V10 series, video input/RGB input/RGB output is available.

2 Web server function supported

Applicable model: V10


*** OS updating is necessary**

<Overview>

V10 on the network can be monitored and operated by starting up a browser(Chrome) on a PC or tablet.

- (1) No browsing software required
 Chrome on PC or tablet is all you need to monitor.
- (2) Asynchronous display
 PC or tablet and V10 unit can display different screens.
- (3) Multiple sessions
 Multiple PCs or tablets can be connected simultaneously. (Max. 10)
- (4) Web pages
 Create dedicated web pages for PC or tablet display with Web Editor.

Simultaneous connections: Max. 10



3 HP printer models added

Applicable model: V10

*** OS updating is necessary**

<Overview>

The number of printer models that can be connected to the V10 series has increased.

For more information, see "https://monitouch.fujielectric.com/img/en/pdf/printer_list_e.pdf"

4 Time server connection supported

Applicable model: V10/V9

*** OS updating is necessary**


<Overview>

Time server connection is now supported. Clocks can be synchronized with a time server.

<Setting location>

Unit: [Date/Time Setting] on the Local mode screen -> [NTP Server Settings] -> [Use NTP Server] is selected.
 Set the NTP Server IP Address and Sync Timing, etc.

Screen data: Project View -> [Hardware Settings] tab -> [MONITOUCH Settings] -> [Calendar/Clock Settings] -> [Use Built-in Clock] is selected.



Function

5 System devices for the unit identification (\$s1019) added

Applicable model: V10/V9/TELLUS5/TELLUS4

<Overview>

You can store the version information in \$s1018 and the identification code of the unit in \$s1019 by setting the value to the system device \$s1016 with MOV macro command.

<System devices>

\$s1016	0: System program version 3: Font version 4: OS version 10: PLC1 driver version 11: PLC2 driver version 12: PLC3 driver version 13: PLC4 driver version	14: PLC5 driver version 15: PLC6 driver version 16: PLC7 driver version 17: PLC8 driver version 18: Simulator version 22: Japanese conversion function(FEP) program version	Write with MOV -> V
\$s1018	Stores version information based on the value set in \$s1016.		V ->
\$s1019	Stores the identification code of the unit on the value set in \$s1016. 1: V9/TELLUS4 2: V10/TELLUS5		NEW V ->

<Example>

Execute \$s1016=4(W) with the switch ON macro



The OS version is stored in \$s1018.

\$s1018=140 represents "OSVer.1.40".

The identification code is stored in \$s1019.

\$s1019=2 represents "V10 series".

6 Barcode reading by camera function supported


Applicable model: TELLUS4(iPad)

<Overview>

QR code/barcode reading using the iPad camera function is now supported.

<Setting location>

Project View -> [Hardware Settings] tab -> [MONITOUCH Settings]
-> [Hardware Settings] -> set [Camera]



7 Printing function of extended data sheet improved

Applicable model: X1, TELLUS5/TELLUS4

■ Clearer text rendering


<Setting location>

Project View -> [Hardware Settings] tab -> [MONITOUCH Settings] -> [Unit Settings] -> [General Settings] -> [Print/PDF output] -> [Make text rendering for printing extended data sheet PDF clear] checkbox

■ Margin adjustment

<Setting location>

Project View -> [Screen] tab -> [Data Sheet] -> [Data Sheet Setting] -> [Use Margin Setting] checkbox and set [Margin Setting]



Configuration Software

1 Tag import from Siemens TIA Portal extended


<Overview>

(1)TIA project files (*.ap19) created with TIA Portal Ver.19 can be imported.

(2)Import is executed only when either of the following is checked in the TIA Portal settings.

- Properties -> Attributes -> Data block accessible from OPC UA
- General -> Attributes -> Usage -> Accessible from HMI /OPC UA /Web API

(3)After executing the import, the total number of tags is displayed.



Configuration Software

2 Trend: Number of points to display increased

Applicable model: TELLUS5

<Overview>

The number of [Points to Display] of trend parts has been increased to max 3840.


When creating a screen of [Size: 3840x2160],
points to display of trend parts can be set up to 3840.

<Setting location>

Trend Parts -> [Graph/Data Settings] -> [Setting] -> [Points to display]

<Note>

Make sure not to set a value larger than "the width" of the trend part. The graph cannot be displayed properly.




3 Multi-languages supported

<Overview>

Menu display in Chinese (Simplified)/Chinese (Traditional)/Korean is now supported.

These languages can be selected when installing on an OS except for Japanese.




4 Operability improved

■ Project View

In a floating state, the editing window is aligned with the left side of the screen.


Double-click or drag and drop to put it back to the original position.



■ Macro Settings

[Cut] [Copy] [Paste] buttons have been added.

Items: Screen
Overlap Library
Screen Library



■ Error Check

If a macro includes an error, it can now be detected by Error Check without opening the macro editor screen.

<Setting location>

Properties in Error Check ->

[Detect error data in macros] checkbox

